



Setting up ProjectWise Configurations

This set of instructions applies only to users that have ProjectWise installed on their computers.

- 1) **Start>Control Panel.**
- 2) If your view is set to 'Category' in the top right drop-down, then select '**Network and Internet**' and click the '**ProjectWise V8i Network**' icon. If your view is set to '... icons' then just search for and click on the '**ProjectWise V8i Network**' icon, as shown below.




- 3) After selecting the ProjectWise icon, the following '**ProjectWise V8i Network Configuration Settings**' window will display.




NOTE: We will set the same settings for both DNS Services and Datasource Listing. The locations will differ based off the location of the computer. i.e If it is in a district, the settings to the district cache server will apply. A list of all servers is provided at the end of this tutorial.

- 4) Under the 'DNS Services' tab enter the **Name**, **Hostname** and **Port**, as shown below, then click the '**Add**' button.

Please Note: Refer to the 'Server Connection Settings Per Area' list at the end of this tutorial to enter the correct server name for your location.



- 5) Next, click on the 'Datasource Listing' tab. The same settings entered in the previous step will be used here as well. Enter the **Name**, **Hostname** and **Port** as shown below and click the '**Add**' button.



- 6) After entering the DNS and Datasource settings, click 'Apply' then 'OK' to connect to the server.

SERVER CONNECTION SETTINGS PER AREA

The following settings apply for both DNS Services and Datasource Listing preferences.

Location	Name	Hostname	Port
District 1	D1CACHE	D1PWCACHE.MDOT.STATE.MS.US	5800
District 2	D2CACHE	D2PWCACHE.MDOT.STATE.MS.US	5800
District 3	D3CACHE	D3PWCACHE.MDOT.STATE.MS.US	5800
District 5	D5CACHE	D5PWCACHE.MDOT.STATE.MS.US	5800
District 6	D6CACHE	D6PWCACHE.MDOT.STATE.MS.US	5800
District 7	D7CACHE	D7PWCACHE.MDOT.STATE.MS.US	5800
Jackson (PWPROD)	PWAPP01	PWAPP01.MDOT.STATE.MS.US	5800
Consultants And Outside Mdot Network			
Domain :	MDOT_PW	PW.MDOT.STATE.MS.US	443

***Note: When logging in for the first time, make sure MDOT\ is showing in front of the username.
If it isn't, it will not log on.